


VOWLER

Quick User Manual - Version 0.2.1 - by Povo

Vowler is a vowel synthesizer. Play it with MIDI, choose a vowel, and shape the voice from soft and round to rough, bright, or distorted.



PLAY A MIDI NOTE > CHOOSE U, O, E, I, OR A > OPEN ADVANCED FOR MORE

QUICK START

- 1 Load Vowler on an instrument or MIDI track.
- 2 Play a MIDI note.
- 3 Choose **U, O, E, I, or A**, or turn the **Vowel** control.
- 4 Click **Advanced** when you want the full sound controls.

INSTALLATION

Platform	Supported	Formats
macOS	macOS 11+ Apple Silicon or Intel	AU, VST3, Standalone
Windows	Windows 10/11 64-bit	VST3, Standalone

macOS

Run the Vowler .pkg installer. It installs:

- /Library/Audio/Plug-Ins/Components/Vowler.component
- /Library/Audio/Plug-Ins/VST3/Vowler.vst3
- /Applications/Vowler.app

Windows

Run the Vowler Windows installer. Keep **All users** (paths below) for the widest DAW support, or choose **Current user** if you do not have an administrator password.

- C:\Program Files\Common Files\VST3\Vowler.vst3
- C:\Program Files\Povoa\Vowler\Vowler.exe

Current user paths: %LOCALAPPDATA%\Programs\Common\VST3\Vowler.vst3 and %LOCALAPPDATA%\Programs\Povoa\Vowler\Vowler.exe. The Portable ZIP can also be copied to the VST3 path.

Unsigned Windows release: for your Povoa Gumroad download, choose More info, then Run anyway. The Portable ZIP avoids the installer/admin, but not Smart App Control or work/school policy.

After installation, restart your DAW or run a full plugin rescan. Vowler appears under the manufacturer Povoa.

SIMPLE VIEW

- **U O E I A** selects a vowel directly.
- **Vowel** moves smoothly between the five vowels.
- Drag the face to move the view. Double-click it to reset.

ADVANCED VIEW

Click **Advanced** to reveal the character, envelope, glide, and output controls.

CONTROL GUIDE

Group	Control	What it does
VOICE	Vowel	Move smoothly between U, O, E, I, and A.
	Mouth	Shift the mouth and vowel shape.
	Growl	Make the voice rougher and heavier.
	Squeak	Add a higher, sharper voice layer.
	Sub	Add octave-down body.
CHARACTER	Drive	Add saturation and intensity.
	Bite	Add harder wave shaping.
	Warp	Stretch and change the formants.
	Pitch	Transpose the sound.
PLAYING	Attack	Set how quickly the note starts.
	Decay	Set the movement from the peak to sustain.
	Sustain	Set the held-note level.
	Release	Set how long the note fades after release.
	Glide	Slide between MIDI notes.
	Output	Set the final level.

Need help? Restart the DAW and run a full plugin rescan.
povoasound.com | info@povoasound.com

Supported formats: macOS AU/VST3/Standalone and Windows VST3/Standalone. VST2, AAX, 32-bit hosts, and native Windows ARM64 hosts are not included.